

# ENGINEERING BULLETIN

## Product Release

New software Version for  
KCM chiller series.

Software Identification–  
KCM\_XXX\_1X\_13.18.18  
(for pCO 5+)  
KCM\_XXX\_1X\_11.18.18  
(for pCO 5)

No: EB/19-20/006,  
Date: 26<sup>th</sup> November 2019

Dear Colleague,

We hereby wish to inform you that the official release of new Software version of KCM\_XXX\_1X\_13.18.18 (for pCO 5+) & KCM\_XXX\_1X\_11.18.18 (for pCO 5).

In this software version, we have made following changes:

- Improved Alarms History management which advance the internal storage management for Alarms, hence problem causing alarms to disappear from alarm history will be resolved.
- Improved communication block which allows controller to have better control over Turbocor compressor.
- Modified trend graph widget, making trend graphs more accurate and precise than earlier version.
- New password management like KSC software, with all functionality like KSC software.
- “Compressor Failed to Run” alarm has been modified and divided in two separate alarm as “Compressor start-up failed” & “Compressor running failed”.
- “Supply voltage low” alarm has been introduced in this software version, this alarm is generated & logged when “DC bus under voltage” and “generator mode active” alarm is generated in compressor.

## Software Release

New software Version for  
KCM chiller series.

Software Identification–  
KCM\_XXX\_1X\_13.18.18  
(for pCO 5+)  
KCM\_XXX\_1X\_11.18.18  
(for pCO 5)