

ENGINEERING SPECIFICATIONS

Document Name: KWS, KAS & KWE New Chiller Software Development		
Document No: ESP-20-21-004	Revision: R00	Date: 08/07/2020
Prepared By: CGH	Approved By: RDT	Sheet: 1

Dear Colleague,

We hereby wish to inform you that the official release of new Software version of

- CONSO_XXX_1X_13.16.16
- CONSO_XXX_2X_13.18.18
- KWE_XXX_1X_13.14.14
- KWE_XXX_2X_13.13.13

In this software version, we have made following changes:

- New password management like KSC software, with all functionality like KSC software.
- Rotational password for factory login with functionality to disable the default password.
- Call for service alarm reset option is provided outside factory login.
- Program revision will be displayed in Main menu display screen.

For more details refer bulletin. EB/20-21/002

1. Call for Service Setting: -

For call for service enable/disable go through below procedure as per shown in flow chart.

Go to factory password page by pressing **Prg + Esc** button,



Enter One day password for "service call" setting then hit enter, you will be taken directly on "service call setting" page as shown in below fig.



Here you can change call for service alarm setting enable\Disable or Trip Runhours.

ENGINEERING SPECIFICATIONS

Document Name: KWS, KAS & KWE New Chiller Software Development		
Document No: ESP-20-21-004	Revision: R00	Date: 08/07/2020
Prepared By: CGH	Approved By: RDT	Sheet: 2

2. Factory Password Enable/Disable: -

Follow below steps.

- Press “prg”
- Select “supervisor” option.
- Unit Configuration.
- Scroll down to the below shown screen.

Here you can enable/disable factory password.



If factory password is disabled, you cannot use the default password for login. In such case you need factory OTP to login.

Log out for such cases will be available on the second last page of Main view as shown in below fig.



This is a day out functionality of OTP login. And once logged out the OTP cannot be used till next calendar day (with different OTP).

ENGINEERING SPECIFICATIONS

Document Name: KWS, KAS & KWE New Chiller Software Development		
Document No: ESP-20-21-004	Revision: R00	Date: 08/07/2020
Prepared By: CGH	Approved By: RDT	Sheet: 3

3. Program revision & Details: -

To see program revision and details scroll down main view menu to last page.

